

The Amateur's Guide to Taking Great Digital Photos



The Shot Doctor: The Amateur's Guide to Taking Great Digital Photos

Copyright © 2009 by Que Publishing

All rights reserved. No part of this book shall be reproduced, stored in a retrieval system, or transmitted by any means, electronic, mechanical, photocopying, recording, or otherwise, without written permission from the publisher. No patent liability is assumed with respect to the use of the information contained herein. Although every precaution has been taken in the preparation of this book, the publisher and author assume no responsibility for errors or omissions. Nor is any liability assumed for damages resulting from the use of the information contained herein.

ISBN-13: 978-0-7897-3948-3 ISBN-10: 0-7897-3948-8

Library of Congress Cataloging-in-Publication Data:

Soper, Mark Edward. The shot doctor : the amateur's guide to taking great digital photos/ Mark Edward Soper. p. cm. Includes index. ISBN 978-0-7897-3948-3 1. Photography—Digital techniques—Amateurs' manuals. 2. Digital cameras—Amateurs' manuals. I. Title. TR267.S653 2009 771.3'3—dc22 2009014446

Printed in the United States of America First Printing: May 2009

Trademarks

All terms mentioned in this book that are known to be trademarks or service marks have been appropriately capitalized. Que Publishing cannot attest to the accuracy of this information. Use of a term in this book should not be regarded as affecting the validity of any trademark or service mark.

Warning and Disclaimer

Every effort has been made to make this book as complete and as accurate as possible, but no warranty or fitness is implied. The information provided is on an "as is" basis. The author and the publisher shall have neither liability nor responsibility to any person or entity with respect to any loss or damages arising from the information contained in this book.

Bulk Sales

Que Publishing offers excellent discounts on this book when ordered in quantity for bulk purchases or special sales. For more information, please contact

U.S. Corporate and Government Sales 1-800-382-3419 corpsales@pearsontechgroup.com

For sales outside the United States, please contact

International Sales international@pearson.com

Associate Publisher Greg Wiegand

Acquisitions Editor Rick Kughen

Development Editor Rick Kughen

Managing Editor Patrick Kanouse

Senior Project Editor

Tonya Simpson

Indexer Ken Johnson

Proofreader Dan Knott

Technical Editor Jay Townsend

Technical Reviewers

Jay Townsend John Freeland Matt Thomas

Publishing Coordinator Cindy Teeters

Book Designer Anne Jones

Compositor Mark Shirar

INTRODUCTION



A BETTER BOOK FOR EVERYDAY PHOTOGRAPHY

Lots of photography books include beautiful photos of exotic locations and scenery. Not this one. I hope you'll enjoy the photos, of course, but I also hope you'll see that the photos included in this book are similar to the ones you've been taking—or would like to take. Graduations, babies, weddings, vacations...the list of photography possibilities goes on—and so do the frustrations.

If you have a digital camera and you're frustrated with your photos, you've opened the right book—I wrote it just for you. Whether you have a modest digital point-and-shoot camera or have laid out the big bucks for a digital SLR with interchangeable lenses (DSLR), you've been taking photos of the most important events in your life—and you've probably been disappointed by the results.

Believe me, I understand. This book was conceived as a result of conversations I had with friends and family who'd gotten new cameras, taken them to special events, and been frustrated by the poor-quality photos they'd taken. I want to help you stop being frustrated with your camera and start enjoying it.

This book is the end result of more than 35 years as a photographer and more than 6 years as a digital camera user. During that time, I've developed a series of recipes I use in different situations to help ensure better photos. And while I prefer to do most of my "serious" shooting with a Canon Digital Rebel XTi DSLR camera, the majority of the photos in this book were shot with various point-and-shoot cameras made by Canon, Nikon, and Kodak; the same types of cameras you use for family, everyday, and vacation photos. In most cases, I provide methods that can be used either with scene-driven cameras or cameras with traditional aperture, shutter, and manual exposure control. To get the most out of this book, I suggest the following:

- Read your camera's manual—This book will tell you how and why to use particular features, but your camera manual provides the nitty-gritty details. I recommend carrying both this book and your camera manual with you.
- Shoot, look, evaluate, and change settings—Digital cameras make seeing your work easy: Photos show up on the LCD display as soon as you take a picture, and you can play back your photos anytime you want. If you've been accustomed to taking a bunch of photos and then reviewing them, it's time for a change. Take a photo or two, look over the pictures, and if you're not satisfied, use the appropriate parts of the book for suggestions. Make those changes and reshoot. I think you'll see a big difference.

2



WHY YOU NEED THIS CHAPTER

If all you want is a picture when the sun is shining, just push the shutter button of your digital camera. But if you want to create daytime photos that people will enjoy viewing, pictures that will bring back special memories of vacations or other special days, you'll want to learn how to use your camera's special features. That's what this chapter is all about.

CHOOSING THE RIGHT APERTURE

The choice of aperture has a big impact on your outdoor photos because it affects the depth of field (how much of the photo is in sharp focus from front to back). If you use Auto or Program mode, you have no choice in aperture settings; with these settings, the brighter the scene, the smaller the aperture and faster the shutter speed. If you're shooting portraits or landscapes, though, you'll want to select your own aperture.

PORTRAITS

For portraits (see Figures 7.1 and 7.2), you want to focus on the subject and blur out the background. To do this, select a wide aperture (f/1.8 to f/5.6) because these apertures have shallower depth of field than narrower apertures. If you cannot select a wide aperture in Aperture Priority mode without overexposing your photo, select a low ISO (200 or less).



Figure 7.1—What's the subject? 1x zoom and f/7.5 aperture combine to make the background rival the subject for sharpness.



Figure 7.2—There's no question about the subject this time! 5x zoom and f/5.6 aperture help blur out the background (ISO 200).

LANDSCAPES

For landscapes (see Figure 7.3), you usually want the entire photo to be in focus. If the landscape has objects at different distances from the camera, you might need to use narrow apertures (f/8.0 and smaller) to achieve the desired depth of field. When you use narrow apertures, you must watch out for shutter speeds that are too slow to hand-hold successfully.



Figure 7.3—A 3x (55mm) lens and narrow f/14 aperture capture both the near bank tree and the far side of the New River Gorge bridge in sharp focus.

CHOOSING THE RIGHT ISO

If you're not worrying about how much of the picture's in focus, you can use Auto ISO or ISO 200 on a sunny day and you'll usually get sharp photos. However, there are situations, even outdoors, where changing to a higher or lower ISO makes sense.

WHEN TO USE A HIGHER (FASTER) ISO

With a higher (faster) ISO, you can use narrower apertures or faster shutter speeds and still have enough light to shoot by, even with very long (10x or longer) zoom lenses.

If your camera cannot provide a hand-holdable shutter speed when you use Aperture Priority and select the aperture you want, you have a couple of choices: Increase the ISO to 400, or use a tripod.

If you are shooting with long lenses (8x or longer; 200mm or longer on most DSLRs; 100mm or longer on Olympus DSLRs), the issue of hand-holdable shutter speeds becomes even more critical: High zoom ratios not only bring distant subjects closer but also magnify every hand tremor. If you find that Auto ISO doesn't let you use a fast enough shutter speed to handhold your long zoom shots, use a higher ISO (400 or greater), enable image stabilization (IS/VR), or use a monopod or tripod.

Using ISO 400 or higher on cloudy days, around dawn, or around dusk also enables you to avoid camera shake, no matter what shooting mode you're using.

WHEN TO USE A LOWER (SLOWER) ISO

If you want to use selective focus techniques outdoors to emphasize your subject, or if you want to use panning to capture a feeling of speed, you might need to use lower ISOs on your camera than what Auto ISO might select when you shoot with 1x-4x zooms. By using a low ISO (ISO 64–200), you can use the limited depth of field created by wide apertures to control what's in focus, or use slower shutter speeds for creative effects (compare Figures 7.4 and 7.5). 68 PART III



Figure 7.4—At ISO 1600, the camera uses an action-stopping 1/320-second shutter speed.




Figure 7.5—At ISO 100, the camera uses 1/25-second shutter speed so you get the sensation of speed from a blurred background).

- → To learn more about choosing ISO settings, see the section "Using ISO Adjustments" on page 122.
- ➔ To learn more about IS/VR technology, see the section "Using Anti-Shake Technologies" on page 196.

CHOOSING THE RIGHT WHITE BALANCE

Here are the rules of thumb for better color outdoors:

- On sunny days, use Auto white balance or, for more vivid colors, use Daylight white balance (see Figure 7.6).
- On overcast days, if you notice the colors are too blue, use Cloudy or Open Shade white balance (see Figure 7.7).
- If your camera has both Cloudy and Open Shade white balance settings, try Cloudy first. Use Open Shade if pictures are too blue when using Cloudy.



- 1. Deeper Blue
- 2. More Intense Green
- 3. More Saturated Gray
- 4. More Vivid Gold

Figure 7.6—Auto white balance (left) produces acceptable colors, but Daylight white balance (right) produces more vivid colors on a sunny day.



Figure 7.7—A comparison of daylight (left) and open shade (right) white balance settings.

You can also use Custom white balance outdoors as well as indoors.



CAUTION If you use Custom white balance, don't forget to check your results frequently. White balance shifts during the day from warm to cool to warm again as you go from sunrise to high noon to sunset. If you don't change Custom white balance when the light changes, you will have off-color photos that will need to be corrected with photo editing software. → To learn more about choosing the best white balance settings, see Chapter 11, "Improving Color."

CHOOSING THE RIGHT SHUTTER SPEED

How important is shutter speed when you're shooting outdoors? It depends on the subject. When you're shooting action, you'll probably want to use shutter speeds of 1/500 second and faster. However, if you're trying to capture the look of moving water, shutter speeds of 1/250 second and slower are better.

LANDSCAPES

Here are some general guidelines for better landscape photos:

White balance: Daylight (preferred) or Auto

ISO: Up to 400

Suggested modes: Aperture Priority (A, Av)

Shutter speed: Set automatically by camera

Aperture: f/1.8 to f/5.6 (selective focus on details); f/5.6 or narrower (overall shot in focus)

Scene mode: Auto, Beach, Snow as needed

Zoom: As needed

Notes: Shoot before 11 a.m. or after 2 p.m. for the best light. Use a tripod or image stabilization (IS) to prevent camera shake.

DIRECTIONAL LIGHTING

The light is lower in the morning and afternoon, and it can provide some outstanding "spotlight" effects, as shown in Figure 7.8.

To get the full benefit of directional lighting, though, make sure you're shooting at an angle where you can see both highlights and shadows. Compare Figures 7.9 and 7.10. RECIPES FOR BETTER DAYTIME PICTURES CHAPTER 7 71



Figure 7.8—The low sun angle brings out the details of the dog and the dog walkers (f/16, 1/60 second, ISO 200, 2x zoom).



Figure 7.9—The sun is to the left of the towboat, so the entire side of the boat is in shadow.



Figure 7.10—Wait just a few seconds, though, and the same subject provides a dramatic mix of light and shadows.

BUILDINGS AND ARCHITECTURE

Here are some general guidelines for better building and architectural photos:

White balance: Daylight (preferred) or Auto

ISO: Up to 400

Suggested modes: Aperture Priority (A, Av)

Shutter speed: Set automatically by camera

Aperture: f/1.8 to f/5.6 (selective focus on details); f/5.6 or narrower (overall shot in focus)

Scene mode: Auto, Beach, Snow as needed

Zoom: As needed

Notes: Shoot before 11 a.m. or after 2 p.m. for the best light. Use a tripod or image stabilization (IS) to prevent camera shake. Use EV adjustment as needed to bring out details.

Figure 7.11 is one of a series I did for a local newspaper on an historic neighborhood. I used +0.3 EV to add a bit more exposure to bring out shadow detail. The morning light brought out building detail and made the flag the center of attention.



Figure 7.11—Deep depth of field, thanks to f/14 aperture and a wideangle lens (22mm, 1.1x), helps capture the essence of a neighborhood in a single shot.

WHY DETAILS MATTER

Overall shots, such as Figure 7.12, help establish the scene, but to capture the real essence of an interesting building or structure, be sure to look for details (see Figure 7.13). I used -0.7 EV in both photos to darken the sky and make the shadows deeper.

RECIPES FOR BETTER DAYTIME PICTURES CHAPTER 7



1. The Detail Shown in Figure 7.13

Figure 7.12— An overall shot of the Lincoln Memorial Bridge in Vincennes, Indiana.

Figure 7.13—Detail of the Lincoln Memorial Bridge. Note how the afternoon light brings out the basrelief.



SHOOTING FROM THE INSIDE TO CAPTURE SPECIAL DETAILS

The early 1900s house shown in Figure 7.14 was decorated for the 4th of July. To capture the unique flavor of the home's rare beveled-pane windows, I took a picture of the bunting through the window.



Figure 7.14— Beveled-pane windows turn any view into a unique experience.

CHILDREN

It's easier to get pictures of children outside, but that doesn't mean it's easy to get good pictures. Follow these guidelines to help you get better photos:

White balance: Daylight (preferred) or Auto when it's sunny; switch to Cloudy or Open Shade when it's overcast

ISO: 200-400 (sunny); 400-800 (overcast)

Suggested modes: Shutter Priority (S, Tv)

Shutter speed: 1/125 to 1/500 or faster

Aperture: Set automatically by camera

Scene mode: Sports, Kids and Pets, or similar action-oriented modes. Use Hi ISO if pictures are too dark or are blurred by camera shake or subject motion.

Zoom: As needed

Notes: Shoot before 10 a.m. or after 2 p.m. for the best light. Use image stabilization (IS) to prevent camera shake. Use Servo or continuous focus.

GET CLOSER...AND USE THE RIGHT FRAMING

Wide-angle shots can cover up the subject with clutter (see Figure 7.15). Use your zoom lens to get in closer for better photos (see Figure 7.16). Figure 7.16 also demonstrates that hold-ing the camera sideways (vertical) works better for some shots.

74

RECIPES FOR BETTER DAYTIME PICTURES CHAPTER 7 75



Figure 7.15—There are children inside the rope ladder. Can you see them? (1.1x zoom)



Figure 7.16—Flip the camera to vertical, zoom in (4x), and now the main subject is easy to see.

...but don't get too close, as shown in Figures 7.17 and 7.18.



Figure 7.17—Too tight a shot makes the viewer feel uncomfortable.



Figure 7.18—Back up a bit and it's easier to see what's going on.

HOW TO UNCLUTTER THE BACKGROUND

Shooting against the sky helps make children at play stand out (Figure 7.19), while using a wide aperture to blur out the background helps capture quieter moments (Figure 7.20).



Figure 7.19—The blue sky makes for a nice contrast with the red T-shirt (12x zoom).



Figure 7.20—This close encounter of the salted-in-the-shell peanut kind uses a 4x zoom and wide f/3.6 aperture to blur out the background.

SHOOTING AT DAWN AND DUSK

Shooting around sunrise or sunset means dealing with rapid changes in lighting, concerns about white balance, and high ISO and low shutter speeds. However, you can get some great photos if you're careful by using these guidelines:

White balance: Daylight (captures the redness in the sky at sunrise and sunset); Cloudy or Open Shade (before sunrise or after sunset; use when skin tones become blue)

ISO: 400–800 before and at sunrise; during and after sunset

Suggested modes: Shutter Priority (S, Tv) or Aperture Priority (A, Av)

Shutter speed: If hand-held, 1/30 second or faster (Shutter Priority); set automatically by camera (Aperture Priority)

Aperture: f/1.8 to f/5.6 (Aperture Priority); set automatically by camera (Shutter Priority)

Scene mode: Sunset while sky is red; Night scene after sunset or before sunrise

Zoom: As needed

Notes: Use image stabilization (IS), a tripod, or a steady surface to prevent camera shake. Use a short (2-second) self-timer if you are not shooting moving subjects.

76

PART III

SUNRISE, SUNSET

No matter how simple or how complex your digital camera is, it's easy to control how intense a sunrise or sunset is: It all depends on where you lock your focus and exposure (see Figure 7.21).



Figure 7.21—Locking exposure on the water, and then raising the camera to aim at the sunset, brings out building detail at the sacrifice of the sunset's intensity (left), while locking exposure on the sky silhouettes the buildings but captures the full majesty of the sunset (right).

• To learn more about exposure lock, see the section "Using Exposure Lock" on **page 116**.



NOTE Be sure to use Sunset scene mode on a scene-driven camera to capture the full color of the sunset.

BUILDINGS AT DUSK

The combination of a fading sunset and brightly lit buildings can provide striking photographs (see Figure 7.22). Be sure to use a tripod or place the camera on a steady surface to avoid camera shake because exposures will often be in the 1/8-second or slower range.

PART III RECIPES FOR BETTER DIGITAL PHOTOS



Figure 7.22—Neon, streetlights, and sunset combine to create a magical view (1/8 second, ISO 400, f/3.6 on a point-and-shoot camera).

BETTER PEOPLE PHOTOS

People and other subjects look better when you avoid front and overhead lighting. For better photos of family and friends of any age, use these tips to supplement the exposure settings needed for the lighting conditions.

AVOID OVERHEAD LIGHTING

I recommend shooting before 10 a.m. and after 2 p.m. because the sun casts longer, more interesting shadows, and with people, it's easier to avoid shadows on the face (see Figure 7.23).



Figure 7.23—High noon is a good time for lunch, not photos. Note the heavy shadows across the face.

78

BACKLIGHT IS FLATTERING, BUT WATCH THE EXPOSURE

Shooting your subjects when they face away from the sun helps the face to relax and captures a halo effect around the hair (see Figure 7.24). In some cases (but not in this photo), you might need to increase exposure by +0.7 to +1.0 EV.



Figure 7.24— Backlighting outlines the subject.

DISTRACTING BACKGROUND? BLUR IT AWAY

One of the reasons I prefer wide-aperture (f/2.8 and faster) lenses is because they make it easier to blur out the back-ground. Compare Figures 7.25 and 7.26.



Figure 7.25—At f/5.6 (2.75x/50mm), the background is distracting.



Figure 7.26—At f/2.8 (2.75x/50mm), the background is blurred out.

On scene-driven cameras, use Portrait mode to help blur out the background.

ACTION AIR-LAND-WATER

Want to capture good action photos? It's harder than it looks. You could just bump up the ISO to 400 or 800, select the fastest shutter speed possible, or select Sports mode and shoot away. This approach will get you a lot of stop-action photos, but they might not convey the feeling of action. To help convey action, try the following techniques.

USING SMOKE

Smoke from historic rifles helps convey the feeling of action in your photos (see Figure 7.27). Water spray from speedboats is also effective (see Chapter 12, "Stopping Action," for details).



Figure 7.27—0.7 EV keeps the foreground from being overexposed, and prefocusing on the squad makes it easier to shoot at the right time.

USING PANNING

Panning helps streak the background for a feeling of speed when shooting fast cars, boats, or airplanes (see Figure 7.28).





Use burst mode to help capture split-second events.

For more about burst mode and panning, see **Chapter 12**, "Stopping Action."



Figure 7.28—When panning a very highspeed subject, like this P-51 warbird, use shutter speeds of up to 1/400 second.

VACATIONS

To make your vacation pictures stand out from the rest, look for unusual ways to view your subjects. Here's a small sampling.

A NEW TAKE ON DISNEY WORLD

The Walt Disney and Mickey Mouse statue is in front of the Disney World Cinderella castle (see Figure 7.29). For a new perspective, I walked next to the statue and saw that Disney was "blessing" his creation (see Figure 7.30).



Figure 7.29—How to get a new perspective on an overdone subject.



Figure 7.30—Change your angle, and see how the subject interacts with the background.

AT THE ZOO

Enclosures can be a big problem (Figure 7.31), but by shooting through or over the fence, or shooting where there is no fence (Figure 7.32), you can get some intriguing photos.



Figure 7.31—The chain-link fence is quite visible, even with a wide aperture (f/4.0) so if possible, try to place your lens against the fence and shoot through a gap in the links.



Figure 7.32—A very limber wild horse.